

## NATURAL RESOURCES CONSERVATION SERVICE

### CONSERVATION PRACTICE STANDARD

## DEEP TILLAGE

(Acres)

CODE 324

### DEFINITION

Performing tillage operations below the normal tillage depth to modify the physical or chemical properties of a soil.

### PURPOSES

This practice may be applied as part of a conservation management system to support one or more of the following:

- Fracture restrictive soil layers.
- Bury or mix soil deposits from water erosion or flood overwash.
- Reduce concentration of soil contaminants, which inhibit plant growth.

### CONDITIONS WHERE PRACTICE APPLIES

This practice applies to land having adverse soil conditions which inhibit plant growth, such as compacted layers formed by field operations, restrictive layers such as claypans, overwash or deposits from water erosion or flooding, or contaminants in the root zone.

This standard includes tillage operations commonly referred to as deep plowing, subsoiling, ripping, or row-till, performed from time to time below the normal tillage depth.

### CRITERIA

#### General Criteria Applicable to All Purposes

Deep tillage operations shall be performed when soil moisture is less than 50 percent of

field capacity, according to the "feel test". (Table 1)

#### Additional Criteria to Fracture Restrictive Soil Layers

Tillage equipment such as chisels, subsoilers, or rippers, with the ability to reach the required depth shall be used.

The depth of tillage shall be a minimum of one inch deeper than the depth of the restrictive layer. Tillage depth should be set carefully and periodically checked to maintain this working depth.

Complete fracturing of the restrictive layer is not required. The fractured zone, as a minimum, shall be sufficient to permit root penetration below the restrictive soil layer. The fractured zone does not need to extend to the row middles and should be limited to the area near the rows.

#### Additional Criteria to Bury or Mix Soil Deposits from Water Erosion or Flood Overwash

Tillage equipment such as moldboard plows, disk plows or chisels with twisted points, with the ability to reach the required depth shall be used.

The tillage operation shall uniformly mix soil 6" or 2 times (2 X) the depth of overwash, whichever is deeper, to achieve a desired available water-holding capacity (AWC) and to break the hydrologic barrier caused by overwash layer.

Conservation practice standards are reviewed periodically, and updated if needed. To obtain the current version of this standard, contact the Natural Resources Conservation Service.

### Additional Criteria to Reduce Concentration of Soil Contaminants or Excess Nutrients

Tillage equipment such as moldboard plows, disk plows or chisels with twisted points, with the ability to reach below the plow layer depth shall be used.

The tillage operation shall mix a sufficient amount of uncontaminated soil with the contaminated material so that the concentration of the contaminant is below the crop tolerance level. Crop tolerance levels shall be established in accordance with West Virginia University guidance and recommendations.

The soil contaminant shall be uniformly distributed throughout the deep tilled layer.

### **CONSIDERATIONS**

Where restrictive layers are a concern, the effects of this practice can be enhanced by including deep rooted crops in the rotation that are able to extend to and penetrate the restrictive layer.

Research on numerous crops has shown that tillage conducted excessively deeper than the compacted layer does not promote increased yields, requires excessive amounts of tillage energy, and promotes future compaction from nearby vehicle traffic.

Reduce or control equipment traffic during periods when soils are prone to compaction and formation of tillage pans.

When infertile flood overwash is mixed with the pre-flood soil profile, the soil rebuilding process can be enhanced by additions of organic matter, such as manure or cover crops utilized as green manure. Crop rotations, tillage and planting systems, which maintain high levels of crop residues, such as no-till, can also accelerate this process.

Where the flood overwash layer is too thick to effectively mix with the pre-flood soil profile, redistribution of the overwash layer by smoothing or removal may be necessary. Generally, no more than about 6 inches of overwash can be uniformly mixed into the soil profile using commonly available equipment. Specialized equipment may be necessary

where greater depths of overwash are to be incorporated.

This practice may impact cultural resources (Archaeological, historic, historic landscape), or wetlands. Follow NRCS national policy and State operating procedures for considering these resources.

### **PLANS AND SPECIFICATIONS**

Specifications for establishment and operation of this practice shall be prepared for each field or treatment unit according to the Criteria, Considerations and Operations & Maintenance described in this standard.

The following specifications will be documented in the conservation plan narrative and/or contract narrative:

Purpose of Tillage

Depth of Tillage

Type of Equipment

### **OPERATION AND MAINTENANCE**

To help reduce compaction, it is desirable to conduct normal tillage operations when soil moisture is less than 50 percent of field capacity. When possible harvest operations should be avoided when soil moisture is greater than 50 percent of field capacity. Field harvest haul traffic should be limited to end rows or haul roads. Compacted regions between crop rows that are not fractured can assist in supporting vehicle traffic, limiting rutting and soil compaction beneath the row.

Deep tillage for reduction of soil compaction shall be performed whenever compaction reoccurs.

When deep tillage has been performed to reduce the concentration of soil contaminants, the contaminate levels in the root zone shall be monitored to assist with determining when or if treatment will be reapplied.